The Light Node Extension Attributes

Overview

This section details the various extension attributes that are found in every *Maya* light shapes. It also explains extension attributes that appear only in area light shapes.

Content:

- Common Extension AttributesArea Light-Specific Extension Attributes

		spotLigh	tShape1		
	spotLight: sp	ootLightShape	21		
L	Sample		Light Shap	e	
	Spot Light Attributes				
	Type S	Spot Light	•		
	Color				
	Intensity	1.000			-
	~	Illuminates	by Default		
	~	Emit Diffus	e N	🖊 Emit Specular	
	Decay Rate	No Decay	-		
	Cone Angle	40.000	—I —		-
	Penumbra Angle (0.000			•
	Dropoff (0.000	•		
	Light Effects				
	Shadows				
	Object Display				
	3Delight				
	Node Behavior				
	UUID				
	Extra Attributes				
	Select			Close	

The location of the 3Delight attributes for a spot light shape.

Common Extension Attributes

 3Delight Diffuse Contribution 	1.000			
Specular Contribution	1.000			
Shadow Objects				
Object Set	<light< td=""><td>/ shadow links></td><td>- k</td><td></td></light<>	/ shadow links>	- k	

3Delight Extension Attributes that exist for all Maya light types.

All Maya lights have the following attributes available in the 3Delight group:

Diffuse Contribution

Specular Contribution

These two attributes allows adjusting the contribution of the light to the diffuse or specular shading components. For instance, setting *Diffuse Contribution* to 0 makes the light a purely specular one; it has the same effect as turing off the light's *Emit Diffuse* control.

Please note that turning off *Emit Diffuse* will make *Diffuse Contribution* controls insensitive; in a similar fashion, turning off *Emit Specular* will make the *Specular Contribution* controls insensitive. The *Emit Diffuse* and *Emit Specular* controls are located in the light shape's main attribute section, a bit below the light's *Intensity* control.

 Spot Light Attributes 	
Type Spot Light 💌	
Color	
Intensity 1.000	
Illuminates by Default	
🖌 Emit Diffuse 🖌 Emit Specular	
Decay Rate No Decay 🔻	
Cone Angle 40.000	

Emit Diffuse and Emit Specular controls must be enabled to allow adjusting the Diffuse Contribution and Specular Contribution, respectively.

Shadow Objects

This attribute allows specifying an object set; only the components of that set will cast shadows from the light. By default, 3Delight for Maya follows normal light linking mechanism for shadowing; this is what will be done when this attribute is set to 'light / shadow linking>'.

Diffuse Contribution	1.000
Specular Contribution	1.000
Object Set	- Shadow Objects
Obiect Set	Zlight / chadow linke> →
Node Behavior	<light links="" shadow=""></light>
UUID	set2
Extra Attributes	Set2

Selecting a Shadow Objects set; the option menu shows all available object sets in the scene.

Area Light-Specific Extension Attributes

In addition to the extension listed above, 3Delight for Maya offers several more attributes for area lights.

▼ 3Delight	
Diffuse Contribution 1.000	
Specular Contribution 1.000	
Sh	adow Objects
Object Set 🛛 <	light / shadow links> 🛛 🔻
Area	Light Geometry ————
Norn	nalize Intensity by Area
Visib	le to Primary Rays
Тwo	Sided
Default Square Primitive	
Sele	ct Geometry

Extension Attributes offered for an area light shape.

Normalize Intensity by Area

When this attribute is off, the *Intensity* attribute controls the amount of light emitted by area unit of the light's geometry. In other words, if an area light is duplicated and scaled to be larger, it will appear to emit more light than the original. Turning this attribute on will scale down the *Intensity* by the light geometry's area. Put differently, it will make the quantity of light emitted by the area light appear constant when it is scaled or set to use a different geometry. This attribute is off by default.

This will make the area light gemoetry visible to primary (aka "camera") rays. Note that the area light geometry won't cast any shadows in the scene.

Two Sided

0

ጠ

When two sided, the areal light will illuminate from both sides of the geometry.

Area Light Geometry

By default, the area light will be shaped as it appears in the *viewport*: a square, altered by the transformation defined for the area light shape. To use any model in the scene to define the shape of the area light, click *Select Geometry*... A new *Select Area Light Geometry* window will appear, containing an outliner.

🛑 😑 Select Area Light Geometry	
<pre></pre>	
Apply Cancel	

The geometry currently set as the area light geometry will be highlighted. By default, nothing is highlighted. Click shapes to select them independently; click groups to select all of their children, or click sets to select all of their members, as the area light geometry. Set members will be flattened - in other words, any set members that are sets will be expanded so their children are used as area light geometry. Click *Apply* to make the selected elements used as the area light geometry list. Click *Cancel* to close the window without modifying the area light geometry list.

Objects listed as area light geometry will not be visible in the final render; they are only used for shaping the area light.
Unless Default Square Primitive appears in the list, the area light shape's transform will be ignored. Each object of the list will retain its position.

Simple shapes with low polygon count should be preferred; more complex area light geometry will require more time to render.

The Select Area Light Geometry window.